

Presenter Quick-Card

LEARN THE WHOLE BIBLE IN 20 HOURS — SLIDE DECKS

Before Class — Setup

- 1 Transfer the lesson-X-deck.html file to your iPad via AirDrop, iCloud Drive, or the Files app.
- 2 Open the file in **Safari** (tap it in the Files app → it opens in Safari).
- 3 Tap the **Share** button (square with arrow) → **"Add to Home Screen"**. This gives you a full-screen app icon with no browser chrome.
- 4 Connect to your TV/projector:
 - **AirPlay:** Swipe down from top-right corner → Screen Mirroring → select your Apple TV or AirPlay device.
 - **HDMI adapter:** Plug in the Lightning/USB-C to HDMI adapter. It mirrors automatically.
- 5 Open the deck from your Home Screen. Confirm slide 1 appears on both screens.
- 6 **Turn off Auto-Lock:** Settings → Display & Brightness → Auto-Lock → **Never**. (Reset after class.)

Advancing Slides

Tap right 2/3 of screen → next slide

Tap left 1/3 of screen → previous slide

Swipe left → next slide

Swipe right → previous slide

With a keyboard connected:

→ **Space** ↓ = Next

← ↑ = Previous

Home = First slide

End = Last slide

Presenter Notes

Press **N** or tap the **N button** (bottom-left corner) to toggle notes.

Notes appear at the bottom of YOUR screen only if you have a keyboard.

On iPad without keyboard, the notes show on the mirrored screen too — toggle them **off** before class starts.

Fullscreen

Press **F** on a keyboard to toggle fullscreen.

From Home Screen icon, it's already fullscreen.

Plan B — PDF Backup

If the HTML deck won't load or Safari misbehaves:

1. Open lesson-X-deck.pdf in the Files app or Books app.
2. Mirror your screen the same way.
3. Swipe to advance pages.
4. It looks identical — nobody will know the difference.

Slide Counter

Bottom-right corner shows your position (e.g., **12 / 54**). Subtle gold — visible to you, invisible to the class at distance.